

Readme (Project4-Group10)

Prerequisites

- Install Node.js on your Computer. <https://nodejs.org/en/download/>
- Install Node Red
 - Open Terminal
 - Run the command below
 - `npm install -g --unsafe-perm node-red`
 - Use `sudo npm install -g --unsafe-perm node-red`
- Open Github(URL). Download the .json file
- Open Terminal
 - Type `node-red`
 - Click on Settings & Click on manage palette
 - Go to install tab
 - Search Dashboard
 - Click on install next to node-red-dashboard

Login to Aws Console

- Find IoT core service
- Go to secure & click on policy
- Click on create policy
- Give any Name to your policy
- In Action type - `iot:*` & Resource ARN - `*`
- Check the Allow checkbox and click on create
- Go to Manage & create a thing
- Click on Create a Thing
- Give any Name to your thing
- Click on Next
- Click on create Certificate
- Download Certificate, Private key & RootCa
- Click on attach policy & attach the policy you created before
- Go to Manage & click on thing
- Click on Interact & Copy the Rest API Endpoint
- It should be something like instance.iot.region.amazonaws.com

Open Terminal & type `node-red`

Check the URL at which your Server is running. It should be something like <http://127.0.0.1:1880/>

Open the URL in the browser

Node Red will open.

Node-Red

- Click on Settings button and click on Import Flows
- Upload the json files you downloaded before
- Flows will be created
- In Flow Subscribe, Click Temperature Node & click on edit

- Paste the Endpoint in the server & Click on edit next to TLS configuration
- Upload the certificate, private key & Root CA
- Go to flow Publish, Click on Temperature node and repeat the same process
- Open timestamp node. In Repeat field, select Interval from the dropdown. Every 5 seconds.
- Click on Deploy.

Open Aws console

- IoT core service
- Click on Test
- In Field Subscribe to topic type Temperature and click on Subscribe to topic
- Click on Publish Topic
- Repeat the same step for Pacemaker, Glucose, Oxygen, Pressure, BloodP, Pedometer & Alcohol
- Click on bars at top right
- Open dashboard to see real time dashboard.